

# Gimmel Physical PortableConnect

## Contents

Getting Started .....	2
PortableConnect with Web Services .....	3
PortableConnect with RFID.....	3
Additional Configuration.....	4
Data Collection .....	4
Data Upload .....	4
Data Update with Web Services .....	5
View Scanned Data .....	5
Clear Scanned Data.....	6
Reconcile.....	6
Web Service Specific Features.....	7
Missing Records .....	7
Picklist .....	8
Load Locations .....	9
RFID Specific Features.....	10
TC51/52 Device Preparation Checklist .....	11
Parts required .....	11
Initialization Steps.....	11

## Version History


Version	Approved By	Effective Date	Product Version	Description of Change
1	Terry Butler	02/18/22	3.11	Created for Gimmel Version 3.11
2	Marta Farensbach	12/1/2022	3.12	Minor updates for Gimmel Physical 3.12
2.1	Marta Farensbach	2/24/2023	3.12	Add checklist and initialization steps

## Getting Started

Gimmal Physical PortableConnect is a barcode/RFID scanning application that allows users to use a portable scanner to perform actions in Gimmal Physical.

To start using PortableConnect:

1. Unlock the portable device.
2. Tap on the Gimmal Physical PortableConnect app icon on the home screen
  - If the app icon is not on the home screen, search the device or open the app drawer and scroll until it is found.
3. Once in the app, tap the vertical ellipses (three dots) in upper right corner and select the desired tab.



## PortableConnect with Web Services

If using PortableConnect with Gimmel Physical Webservices, you will need:

- URL for the Gimmel Physical Webservice
- Valid Gimmel Physical login credentials


To use:

1. Go to the Preferences tab.
2. Enable 'Using Web Services' and 'Using Web Sync'
3. Enter the Webservice URL in the 'Webservice:' textbox.
4. Enter the Gimmel Physical credentials in the 'Username:' and 'Password' textboxes respectively.
5. Tap on the 'Save' button at the bottom of the page.

## PortableConnect with RFID

To enable using PortableConnect with RFID:

1. Go to the Preferences tab.
2. Ensure webservices are enabled. See PortableConnect with Webservices.
3. Select the appropriate device from the 'Barcode Device' dropdown.
4. Enable 'RFID'.




The screenshot shows the Gimmel Preferences screen. At the top, there is a header with the Gimmel logo and a menu icon. Below the header, there is a section for 'Webservice:' with a text input field. A separator line is followed by the text 'USING BASIC AUTHENTICATION'. Below this, there are two text input fields for 'Username:' and 'Password:'. A dropdown menu for 'Barcode Device' is set to 'RFID'. Below the dropdown, there are three toggle switches: 'RFID' (checked), 'Power' (unchecked), and 'Beep' (unchecked). Below these, there is a section for 'Bluetooth Barcode Reader' with the status 'Not Connected' and a toggle switch (checked). At the bottom, there are five more toggle switches: 'Using Web Services' (checked), 'Use Web Sync' (checked), 'Load Locations' (checked), 'Allow Duplicate Scans' (checked), and 'Use Detailed Logging' (checked). A 'SAVE' button is located at the very bottom of the screen.

## Additional Configuration

- Allow Duplicate Scans: If this setting is enabled, PortableConnect will not automatically remove multiple scans of the same item.

## Data Collection

To begin scanning barcodes, select Collection from the menu.




1. Set the Transfer Destination:
  - a. Check the 'Make next scan a location' checkbox.
  - b. Scan the barcode of the location to transfer items.
  - c. If the location is successfully set, you will see the barcode scanned next to the 'Location:' label.
2. Scan the barcodes of the items to be transferred:
  - a. If the barcode label is damaged or won't read, you can type it manually into the 'Type or Scan Barcode' text box. The barcode will be logged once the enter key is hit.
3. Repeat the above process for all items to be scanned.

## Data Upload

To generate a file of the transfers for upload to the Gimmel Physical application:

1. Select Create File from the menu.
2. To remove scans from the log, check the 'Clear scans after creation' checkbox.
3. Tap the 'GENERATE FILE' button.


A text file named TransferData.txt will be created in the Install Directory/Gimmel Physical Portable that can be uploaded through the Gimmel Physical Web UI.



## Data Update with Web Services

When using Webservices there's no need to generate a file. The scans can be uploaded directly from the device.

1. Go to the Synchronize tab.
2. Ensure the upload type is set to '(TRANSFER)'.
3. Tap the 'UPLOAD' button.
4. The results of the upload will be listed below.




## View Scanned Data

All scans are saved to a log on the device.

To view the logged scans:

1. Select History from the menu.
2. The barcode and scan date will be listed in order of scan.




## Clear Scanned Data

Once transfers are successfully uploaded, clear the scanned data log:

1. Select Clear from the menu.
2. Tap the 'CLEAR' button.

If there is other data saved to the device from using Webservices, you can clear from this option as well.

1. Select Clear from the menu.
2. Tap 'RESET ALL DATA'.



## Reconcile

A reconcile compares scanned data for a given location to what Gimmel Physical expects in that location, then updates Gimmel Physical to be in sync with the scanned data.

1. Scan a location barcode.
2. Scan the barcodes for all items in the location.
3. Upload the scanned data.
  - a. Without webservices:
    1. Create a text file as detailed in the Data Upload section.
    2. Copy the file to your workstation.
    3. Upload the file through the Gimmel Physical web site.
  - b. With webservices:
    1. Go to the Synchronize tab.
    2. Ensure the upload type is set to '(Reconcile)'.
    3. Tap the 'UPLOAD' button.
    4. The results of the reconcile will be listed below.

A reconcile has three possible results:

1. The scanned item is in the expected location.
  - a. No action is taken.
2. Gimmel Physical found a scanned item that was not expected in that location.
  - a. Gimmel Physical will transfer the item to the scanned location.
3. Gimmel Physical expected an item, but it was not found in the scanned data.
  - a. Gimmel Physical will mark the item as missing.

## Web Service Specific Features

To use these features Webservices must be configured as detailed under PortableConnect with Webservices in this document.

### Missing Records

To view a list of missing records in Gimmel Physical via PortableConnect:

1. Select the Missing tab.
2. Select the item tab to view missing items.
3. The items will populate below (see right).

If using RFID with PortableConnect, a 'DETECT' button will appear upon tapping on the item.

Tapping the 'DETECT' button will change the tab to the Detector tab and preload the item barcode. See PortableConnect with RFID for more information.




## Picklist

PortableConnect with Webservices can be used to fulfill valid requests in Gimmal Physical.

1. Navigate to the Picklist tab.
2. Select the item tab to view valid requests for.
3. Tap on the request to mark as fulfilled.
4. Tap the 'TRANSFER' button.

This will add the appropriate barcodes to the log and mark the request as complete on the device. To complete the request and update Gimmal Physical an upload must be performed.





If using RFID with PortableConnect: a 'DETECT' button will appear on the request. Tapping the 'DETECT' button will change the tab to the Detector tab and preload the item barcode. See PortableConnect with RFID.




## Load Locations

When using Webservices, PortableConnect can preload the list of possible locations from Gimmal Physical.

1. Go to the Preferences tab.
2. Enable 'Load Locations'
3. Tap 'SAVE'.
4. Go to the Locations tab.
5. Tap 'DOWNLOAD LOCATIONS'; Wait for the download to complete.
6. Navigate to the Collection tab.
7. Tap the 'SELECT' button adjacent to the 'Locations:' label.
8. Select the location's item tab.
9. Tap a location from the list to prepopulate the location.





## RFID Specific Features

Detector: PortableConnect with RFID can be used to locate missing items.

1. Navigate to the Detector Tab.
2. Enter the barcode of the item to locate.
3. Tap 'READY TO SCAN'.

The device will beep if you are within range of the item and increase beeping the closer the device becomes.



## TC51/52 Device Preparation Checklist

### Parts required

- TC51 or TC52 Scanner
- Docking Station
- USB cable
- Power cable (three parts)

### Initialization Steps

- 1) Assemble the power cable:
  - a) Connect the three power cable pieces.
  - b) Plug the power cable into the dock.
  - c) Plug the power cable into a wall outlet.
- 2) Connect the USB cable to the dock and a PC.
- 3) Install battery into the back of the scanner.
- 4) Dock the scanner and allow it to charge.  
Note: Full battery is ideal, but not required.
- 5) Once the scanner powers on, go to the Settings and update the Date and Time.  
Note: *Automatic* should be disabled while setting the date and time, and then re-enabled once it is accurate.
- 6) Swipe down from the top of the scanner (while it is still docked) and change the USB connection type to *Transfer Files*.
- 7) Copy the latest version of the APK that was delivered with these instructions. Paste it directly into the Internal shared storage drive of the scanner.
- 8) Install the APK:
  - a) Take the scanner out of the dock.
  - b) Unlock the scanner.
  - c) Navigate to the Home Screen, and swipe up from the bottom to get to the App Drawer.
  - d) Locate the File Browser app and browse to the top directory of Internal shared storage.
  - e) Double-click on the Gimmel.GimalPortableConnect.apk and follow the installation steps.
  - f) Select Open as the last step.
- 9) Select the square in the bottom-right corner and then use the Clear All button to reset the Gimmel Portable Connect app.
- 10) To locate the Gimmel Portable Connect app, navigate to the Home Screen and swipe up from the bottom  
Note: For easier access, tap and hold and then drag the app icon onto the Home Screen
- 11) We recommend adding the Settings to the Home Page of the scanner for easier troubleshooting.