

Gimmel Physical

Contents

FileConnect.....	1
Overview	1
Windows Service.....	1
Manage Directories.....	2

Version History

Version	Approved By	Effective Date	Description of Change
3.11	Terry Butler	03/01/2022	Created for Gimmel Version 3.11

Overview

FileConnect allows users to configure a service that automatically imports records into Gimmel Physical.

FileConnect is comprised of 2 components

1. FileConnect (user interface) and the
2. FileConnect Service (Windows service)


FileConnect allows users to:

- Start and stop the FileConnect service
- Change web services settings
- Configure monitored directories

The FileConnect Service monitors the directories specified in the user interface for files that match certain criteria. When a new file is detected in a monitored directory, the FileConnect Windows service will use the Gimmel web service to upload the file and import the data it contains into the Gimmel web application.

Windows Service

1. In File Connect start the Windows service by clicking Start or stop the service by clicking Stop. (The service can also be controlled through the Windows Service application)
2. The Status of the service is displayed (Running or Stopped) in FileConnect.
3. To have the service started automatically check the checkbox 'Auto-start service when OS starts'.



Web Service Settings



- Username – the username for connecting to the web service.
- Password – the password for connecting to the web service.
- Web Service URL – the URL for the Gimmel Physical web service
- Web Service settings are saved by clicking on the Save button below the Web Service URL.

Manage Directories

1. Click Manage Directories to see the directories that FileConnect is managing.
2. To add a new monitored directory click the Add button. To edit or delete a monitored directory click the corresponding button.



3. When adding or editing a monitored directory, fill in the required information on the Directory detail page.



Name:

Directory: ...

File Name Mask:

Notify Email:

Import Profile: ▼

Post Import Action: ▼

Days To Keep Archived Files: ▼

Queue Labels:

Gimmel Web Service Address <https://gimmaldemo310-services.infolinx.com>

Ok Cancel

Directory Settings

- Name – the display name (in FileConnect and notification emails) of the monitored directory.
- Directory – the full path of the directory to monitor.
- Path can be a local folder or network share in UNC path.



- If UNC path used, user identity running FileConnect service must have read/write access to network share.
- File Name Mask – an expression used to filter the files within the directory. * is used as a wildcard. For example, if the mask is *.txt, then only .txt files will be processed. A value of *.* will result in all files being processed.
- FileConnect requires a mask value to be provided, an empty string (i.e. blank) will not work.
- Notify Email – the email address to which data import notifications will be sent.
- Interchange Profile – the import profile to use when importing data from files in this directory.
- Post Import Action – Archive or Delete; Archive will put processed files in the Processed folder (a subdirectory under the monitored directory); Delete will remove processed files.
- Days to Keep Archived Files – If Archive is selected for Post Import Action, then this setting governs how many days to keep files in the Processed folder. After the specified number of days has elapsed, the old files will be deleted. If Delete is selected for Post Import Action, then this setting will be disabled.
- Queue Labels – determines whether labels will be queued in the Gimmel web application when new items are created from files in this directory.
- Click OK to save the monitored directory or click Cancel to discard changes and exit.